# WSA4000 CLI (Command Line Interface) Program Documentation

Generated by Doxygen 1.7.4

Mon Aug 29 2011 14:11:58

CONTENTS 1

## **Contents**

1	Introduction						
2	Data	Data Structure Index					
	2.1	Data S	Structures	. 2			
3	Data	a Structure Documentation					
	3.1 wsa_descriptor Struct Reference			. 2			
		3.1.1	Detailed Description	. 3			
		3.1.2	Field Documentation	. 3			
	3.2	wsa_d	levice Struct Reference	. 4			
		3.2.1	Detailed Description	. 4			
		3.2.2	Field Documentation	. 4			
	3.3	wsa_fr	rame_header Struct Reference	. 5			
		3.3.1	Detailed Description	. 5			
		3.3.2	Field Documentation	. 5			
3.4 wsa_		wsa_re	esp Struct Reference	. 6			
		3.4.1	Detailed Description	. 6			
		3.4.2	Field Documentation	. 6			
3.5 wsa socket Struct Reference		ocket Struct Reference	. 7				
		3.5.1	Detailed Description	. 7			
		3.5.2	Field Documentation				
		wsa tii	me Struct Reference				
		3.6.1	Detailed Description				
		3.6.2	Field Documentation				

## 1 Introduction

This documentation, compiled using Doxygen, shows in details the code structure of the CLI (Command Line Interface) tool. It provides information on all the libraries involved.

The following diagram illustrates the different layers and libraries involved in interfacing with a WSA on the PC side.

2 Data Structure Index 2




Figure 1: Interface Layers to WSA on PC Side

The CLI interfaces to a WSA through the wsa\_api library, which provides functions to set/get particular settings or data from the WSA. The wsa\_api encodes the commands into SCPI syntax scripts, which are sent to a WSA through the wsa\_lib library. Subsequently decodes any responses or packet coming back from the WSA through the wsa\_lib.

The wsa\_lib, thus, is the main gateway to a WSA box from a PC. The wsa\_lib has functions to open, close, send/receive commands, querry the WSA box status, and get data. In this CLI version, wsa\_lib calls the wsa\_client's functions in the transport layer to establish TCP/IP specific connections. Other connection methods such as USB could be added to the transport layer later on. The wsa\_lib, thus, abstracts away the interface method from any application/presentation program calling it.

The CLI, hence, is a direct example of how the wsa api library could be used. Data will

The WSA4000 CLI is designed using mixed C/C++ languages. The CLI when executed will run in a Windows command prompt console. List of commands available with the CLI is listed in the print cli menu() function.

#### Limitations in v1.0:

The following features are not yet supported with the CLI:

- · DC correction. Need Nikhil to clarify on that.
- · IQ correction. Same as above.
- Automatic finding of a WSA box(s) on a network.
- · Set sample sizes. 1024 size for now.
- · Triggers.
- · Gain calibrarion. TBD with triggers.
- · USB interface method might never be available.

## 2 Data Structure Index

#### 2.1 Data Structures

Here are the data structures with brief descriptions:

wsa_descriptor (This structure stores WSA information )	2
wsa_device (A structure containing the components associate with each WSA device )	4
wsa_frame_header (This structure contains header information related to each frame read by wsa_get_frame() )	5
wsa_resp (This structure contains the response information for each query )	6
wsa_socket (A structure containing the socket parameters used for creating TCP/IP connection for control and data acquisition )	7
wsa_time (This structure contains the time information. It is used for the time stamp in a frame header )	7

## 3 Data Structure Documentation

## 3.1 wsa\_descriptor Struct Reference

This structure stores WSA information.

#### **Data Fields**

- char prod\_name [50]
- char prod\_serial [20]
- char prod\_version [20]
- char rfe\_name [20]
- char rfe\_version [20]
- char fw\_version [20]
- char intf\_type [20]
- uint64\_t inst\_bw
- uint64\_t max\_sample\_size
- uint64\_t max\_tune\_freq
- uint64\_t min\_tune\_freq

## 3.1.1 Detailed Description

This structure stores WSA information.

#### 3.1.2 Field Documentation

#### 3.1.2.1 char fw version

The firmware version currently in the WSA.

3.1.2.2 uint64\_t inst\_bw

The WSA instantaneous bandwidth in Hz.

3.1.2.3 char intf\_type

The interface method to a WSA. Available: "TCPIP" ("USB" TBD).

3.1.2.4 uint64\_t max\_sample\_size

The maximum number of continuous I and Q data samples the WSA can capture per frame.

3.1.2.5 uint64\_t max\_tune\_freq

The maximum frequency in Hz that a WSA's RFE can be tuned to.

3.1.2.6 uint64\_t min\_tune\_freq

The minimum frequency in Hz that a WSA's RFE can be tuned to.

3.1.2.7 char prod name

WSA product name.

3.1.2.8 char prod\_serial

WSA product serial number.

3.1.2.9 char prod\_version

WSA product version number.

3.1.2.10 char rfe name

WSA product name.

3.1.2.11 char rfe\_version

WSA product version number.


The documentation for this struct was generated from the following files:

- · wsa api.h
- wsa\_lib.h
- wsa\_lib.txt

#### 3.2 wsa\_device Struct Reference

A structure containing the components associate with each WSA device.

Collaboration diagram for wsa\_device:



#### **Data Fields**

- struct wsa\_descriptor descr
- struct wsa\_socket sock

## 3.2.1 Detailed Description

A structure containing the components associate with each WSA device.

#### 3.2.2 Field Documentation

#### 3.2.2.1 struct wsa\_descriptor descr

The information component of the WSA, stored in wsa\_descriptor.

## 3.2.2.2 struct wsa\_socket sock

The socket structure component of the WSA, used for TCPIP connection.


The documentation for this struct was generated from the following files:

- wsa\_api.h
- wsa\_lib.h
- wsa\_lib.txt

#### 3.3 wsa\_frame\_header Struct Reference

This structure contains header information related to each frame read by wsa\_get\_frame().

Collaboration diagram for wsa\_frame\_header:



#### **Data Fields**

- char prod\_serial [20]
- uint64\_t freq
- char gain [10]
- uint32\_t frame\_size
- struct wsa\_time time\_stamp

#### 3.3.1 Detailed Description

This structure contains header information related to each frame read by wsa\_get\_frame().

#### 3.3.2 Field Documentation

## 3.3.2.1 uint32\_t frame\_size

Number of {I, Q} samples pairs per WSA data frame.

## 3.3.2.2 uint64\_t freq

The center frequency (Hz) to which the RF PLL is tuned.

#### 3.3.2.3 char gain

The amplification in the radio front end at the time a WSA data frame is captured.

#### 3.3.2.4 char prod serial

WSA product version number.

#### 3.3.2.5 struct wsa\_time time\_stamp

The time when a data frame capture begins, stored in wsa\_time structure.

The documentation for this struct was generated from the following files:

- · wsa api.h
- wsa\_lib.h
- wsa\_lib.txt

#### 3.4 wsa\_resp Struct Reference

This structure contains the response information for each query.

#### **Data Fields**

- int64 t status
- char \* result

#### 3.4.1 Detailed Description

This structure contains the response information for each query.

#### 3.4.2 Field Documentation

#### 3.4.2.1 char result

The resulted string responded to a query.

#### 3.4.2.2 int32\_t status

The status of the query. Positive number when success, negative when failed.

The documentation for this struct was generated from the following files:

- · wsa\_lib.h
- wsa\_lib.txt

## 3.5 wsa\_socket Struct Reference

A structure containing the socket parameters used for creating TCP/IP connection for control and data acquisition.

## **Data Fields**

- SOCKET cmd
- SOCKET data

#### 3.5.1 Detailed Description

A structure containing the socket parameters used for creating TCP/IP connection for control and data acquisition.

#### 3.5.2 Field Documentation

#### 3.5.2.1 SOCKET cmd

The command socket for command controls and queries. The string protocol used for this socket is HISLIP.

#### 3.5.2.2 SOCKET data

The data socket used for streaming of data

The documentation for this struct was generated from the following files:

- · wsa\_api.h
- · wsa lib.h
- wsa\_lib.txt

#### 3.6 wsa\_time Struct Reference

This structure contains the time information. It is used for the time stamp in a frame header.

## Data Fields

- int32\_t sec
- uint32\_t nsec

## 3.6.1 Detailed Description

This structure contains the time information. It is used for the time stamp in a frame header.

## 3.6.2 Field Documentation

## 3.6.2.1 int32\_t nsec

Nanoseconds after the second (0 - 999 999 999).

#### 3.6.2.2 int32\_t sec

The number of seconds elapsed since 00:00 hours, Jan 1, 1970 UTC.

The documentation for this struct was generated from the following files:

- wsa\_api.h
- wsa\_lib.h
- wsa\_lib.txt

# Index

sec

cmd wsa_socket, 7	wsa_time, 8 sock				
data wsa_socket, 7	wsa_device, 4 status wsa_resp, 6				
descr					
wsa_device, 4	time_stamp wsa_frame_header, 6				
frame_size					
wsa_frame_header, 5	wsa_descriptor, 2				
freq wsa frame header, 5	fw_version, 3				
fw_version	inst_bw, 3 intf_type, 3				
wsa_descriptor, 3	max_sample_size, 3				
woa_accompton, c	max_tune_freq, 3				
gain	min_tune_freq, 3				
wsa_frame_header, 6	prod_name, 3				
	prod_serial, 3				
inst_bw	prod version, 3				
wsa_descriptor, 3	rfe_name, 3				
intf_type	rfe_version, 3				
wsa_descriptor, 3	wsa_device, 4				
max sample size	descr, 4				
wsa_descriptor, 3	sock, 4				
max_tune_freq	wsa_frame_header, 5				
wsa_descriptor, 3	frame_size, 5				
min_tune_freq	freq, 5				
wsa_descriptor, 3	gain, 6				
_ ,	prod_serial, 6				
nsec	time_stamp, 6				
wsa_time, 8	wsa_resp, 6				
	result, 6				
prod_name	status, 6				
wsa_descriptor, 3	wsa_socket, 7				
prod_serial	cmd, 7				
wsa_descriptor, 3 wsa_frame_header, 6	data, 7				
prod_version	wsa_time, 7				
wsa_descriptor, 3	nsec, 8				
waa_descriptor, o	sec, 8				
result					
wsa_resp, 6					
rfe_name					
wsa_descriptor, 3					
rfe_version					
wsa_descriptor, 3					